

### 5.3 Cross Trading Device Trades Enquiry (Static)

If the Exchange Participants had subscribed "Cross Trading Device Enquiry", this enquiry allows specific users to view all trades since the start of the trading, performed by another BSS, ETTSS or first/second terminal. Supervisor enters broker number. He may optionally specify time, market code or security code. The trades are displayed in time sequence. Rejected trades are excluded from the enquiry. The trades are grouped in purchase order followed by sale order, within market code. The 'Trade Totals' for each distinct currency are shown.


# For Exchange's customized-keyboard:

Step1: Press PRE/SP
Step2: Press TRAN ENQ
Step3: Input Data
Step4: Press ENTER

# For 101-keyboard:

Step1: Press F9
Step2: Press F12
Step3: Input Data
Step4: Press ENTER

## Exchange's customized-keyboard



#### Fields for user reference

E: LIN	1-	INI/OUT	0 1: 1 /	
Field Name	Туре	IN/OUT	Optional /	Remarks
			Mandatory	
BROKER	Number (4)	IN	Mandatory	Broker Number
				Mandatory field for cross trading device enquiry
START TIME	HH:MM	IN	Optional	Trade Time Filter
				ETTSS will display the trades after the START TIME input
				By default 00:00 will show all trades
MKT	Characters (4)	IN	Optional	Market filter, STOCK must be blank when used
				MAIN = Main market
				GEM = GEM Market
				ETS = Extended Trading Securities
				NASD = NASDAQ
STOCK	Number (5)	IN	Optional	Security Code FILTER, MKT must be blank when used
				Will show all trades if it is left blank



Step 1 & Step 2



#### Step 3& Step 4 (With selected broker)





Step 3& Step 4 (With selected broker with stock and time filtered)





#### **Remarks for Cross Trading Device Orders Enquiry (Static)**



ID	Field Name	Remarks		
01	Туре	Trade Type		
		1 <sup>st</sup> Char = Shortsell Indicator		
		C = Shortsell Cover		
		N = Non-shortsell		
		M = Market Maker Shortsell		
		A = Index Arbitrage Shortsell		
		F = Stock Futures Hedging shortshell		
		2 <sup>nd</sup> Char = Private Trade Type		
		A = Auto match		
		M = Manual (Price within normal range)		
		S = Manual (Price outside normal range)		
		Q = Special Lot		
		P = Odd Lot		
		E = Semi-automatic spread lot		
		O = Semi –automatic odd lot		
		V = Overseas trade		
		R = Pre-open		
		3 <sup>rd</sup> Char = Public Trade Type		
		X = direct business trade		
		Blank = non-direct trade		
02	TC	Origin Indicator		
		A = Agency		
		P = Principal		
		Blank = None		